



i4™

Setting up i4 to Work with Microsoft® Windows 7/8

November 16, 2013



© 2013 Jonas Fitness or its affiliates. All rights reserved. This work is confidential and its use is strictly limited. Use is permitted only in accordance with the terms of the agreement under which it was furnished. Any other use, duplication, or dissemination without the prior written consent of Jonas Fitness or its affiliates is strictly prohibited. The information contained herein is subject to change without notice. Except as specified by the agreement under which the materials are furnished, Jonas Fitness and its affiliates do not accept any liabilities with respect to the information contained herein and is not responsible for any direct, indirect, special, consequential or exemplary damages resulting from the use of this information. No warranties, either express or implied, are granted or extended by this document.

<http://www.jonasfitness.com>

Jonas Fitness is a registered trademark of Jonas Software

i4 is a common trademark of Jonas Fitness.

Other brands and their products are trademarks or registered trademarks of their respective holders and should be noted as such.

Limits of Liability and Disclaimer: While every precaution has been taken in the preparation of this document, Jonas Fitness, a division of Jonas Software, the editors and authors assume no responsibility for errors or omission. Neither is any liability assumed for damages resulting from the use or misuse of the information contained herein.

Contents

Introduction	4
Setting up the Internet Explorer Browser	5
Setting up i4 to Work with Finger Prints	13
Installing DigitalPersona One Touch RTE	13
Installing the JFI Fingerprint Component	18
Installing the JFI Camera Utility	20
Installing the Serial Control Component 2	21


Introduction

This document provides instructions for setting up the drivers and components for i4 in the Windows 7/8 environments.



Important: The installation processes for the drivers not documented in this guide are the same as installing those drivers in a Windows XP environment.


All drivers and components for i4 are available using the Support tab on the i4 front counter support page



Setting up the Internet Explorer Browser


Follow these steps to set up the Internet Explorer (IE) browser for use with Windows 7/8.

1. Turn on the compatibility View for apheion front counter site:
 - To turn on the compatibility mode, browse <https://aphelion.aphelionasp.net/>.
 - Click the compatibility view button.




Note: Turning on compatibility mode will correct all display related problems like out of place menus, images, text boxes and buttons.


2. On browser setting make sure the site apheion.aphelionasp.net is added to trusted site:
 - Select Internet Options from the IE menu. The Internet Options dialog box appears.




- Click the Security tab.
- Click the Trusted sites zone.




- Click the **Sites** button. The Trusted sites dialog box appears.




- In the Add this website to the zone field, enter https://aphelion.aphelionasp.net/.




- Click the **Add** button. The site is added to the list.
- Click the **Close** button. The Internet Options dialog box appears with the Security tab on top.
- Click the **Custom level** button. The Security Settings – Trusted Sites Zones dialog box appears.




- In the Reset custom settings area, change the setting to Low.



- Click the **Reset** button. A Warning! Message pops up.
- Click the **Yes** button.
- Update the ActiveX controls and plug-ins settings as follows.





- Click the **OK** button.

Setting up i4 to Work with Finger Prints


Setting up i4 to work with finger prints is a 2-step process:

- [Installing DigitalPersona One Touch RTE](#)
- [Installing the JFI Fingerprint Component](#)


Installing DigitalPersona One Touch RTE

To install DigitalPersona One Touch RTE, follow these steps:


1. Sign on to i4.
2. Open the support page.
3. Select the DigitalPersona One Touch RTE Installer.




4. Save it to a local folder.
5. Unzip the DigitalPersona_One_Touch_RTE.zip to a local folder.
6. Right click the setup.exe file.



7. Click the Run as Administrator option. The Welcome dialog box appears.




8. Click the **Next** button. The License Agreement dialog box appears.



9. Click the I accept the terms in the license agreement option.
10. Click the **Next** button. The Destination Folder dialog box appears.




11. Click the **Next** button. The Custom Setup dialog box appears.




12. Click the **Next** button. The Java Runtime Environment dialog box appears.



13. Click the **Next** button. The Ready to Install the Program dialog box appears.



14. Click the Install button. When the installation is completed, the InstallShield Wizard Completed dialog box appears.



15. Click the **Finish** button.




Important: If a restart is required, restart your computer to complete the installation.

Installing the JFI Fingerprint Component

To install the JFI finger print component, follow these steps:

1. On the support page, select the JFI Fingerprint Component.




2. Save it to a local folder.
3. Unzip the DigitalPersona_One_Touch_RTE.zip to a local folder.
4. Right click the setup.exe file.
5. Click the Run as Administrator option. The Welcome dialog box appears.
6. Run the Wizard accepting all of the defaults.

Installing the JFI Camera Utility

To install the JFI camera utility, follow these steps:

1. On the support page, select the JFI Camera Utility.




2. Save it to a local folder.
3. Unzip the JFI_Image_Capture_Installer.zip to a local folder.
4. Right click the setup.exe file.
5. Click the Run as Administrator option. The Welcome dialog box appears.
6. Run the Wizard accepting all of the defaults.

Installing the Serial Control Component 2

To install the serial control component 2 for the serial port barcode reader, follow these steps:

1. On the support page, select the Serial Control Component 2 option.



2. Save it to a local folder.
3. Unzip the Serial_Control_Component_2.zip to a local folder.
4. Right click the setup.exe file.
5. Click the Run as Administrator option. The Welcome dialog box appears.
6. Run the Wizard accepting all of the defaults.